Internet Explorer Vam ne otvara štampu dokumenta

Poslednja izmena 19/07/2021 1:09 pm CEST

Ukoliko se nađete u situaciji da Vam Internet Explorer ne otvara štampu dokumenata, otvori se stranica koja pokazuje crni/sivi prozor bez dokumenta za štampanje ili se dokumenti loše ispisuju vrlo verovatno su se tokom ažuriranja programa postavke aplikacije Adobe Reader-a izbrisale.

Prvi korak koji treba uraditi je brisanje istorije pretraživanja.

To možete napraviti **u Podešavanjima pretraživača** (Tools Alt + X)) klikom na **Internet options** kliknete na dugme Settings (uokvireno na slici 1) i nakon toga obrišete istoriju pretraživanja (slika 2)

	Security	Privacy	Content	Connections	Programs	Advanced
						And the second s
Home p	bage —			2 HH V. CONTRACT		20
	To crea	ate home	page tabs,	type each add	ress on its o	own line.
0	http:	//go.micr	osoft.com	/fwlink/p/?Lin	kld=255141	1 6
						Y
		Use cu	rrent	Use default	Use n	ew tab
Startu	n	-				
Janu	a. a. 111 a.	1.6.1		23		
05	tart with ta	abs from t	ne last ses	sion		
() S	tart with h	ome page				
Tabs -					-	
Char	nge how we	ebpages a	re displaye	ed in tabs.	Ta	abs
_						
Browsi	ng history	-				
Browsi Dele	ng history te tempora	ry files, h	istory, cool	kies, saved pas	swords, and	d web
Browsi Dele form	ng history te tempora informatio	ry files, h n.	istory, cool	kies, saved pas	swords, and	d web
Browsi Dele form	ng history te tempora informatio Delete brow	ry files, h n. sing histo	istory, cool ry on exit	kies, saved pas	sswords, and	d web
Browsi Dele form	ng history te tempora informatio Delete brow	ry files, h n. sing histo	istory, cool ry on exit	kies, saved pas Delete	swords, and	d web
Browsi Dele form	ng history te tempora informatio belete brow	ry files, h n. sing histo	istory, cool ry on exit	kies, saved pas Delete	swords, and	d web tings
Browsi Dele form	ng history te tempora informatio Delete brow	ry files, h n. sing histo	istory, cool ry on exit	kies, saved pas Delete	swords, and	d web tings
Browsi Dele form	ng history te tempora informatio Delete brow Colors	ry files, h n. sing histo	istory, cool ry on exit guages	kies, saved pas Delete Fonts	swords, and	d web tings ssibility
Browsi Dele form	ng history te tempora informatio Delete brow Colors	ry files, h n. sing histo	istory, cool ry on exit guages	kies, saved pas Delete Fonts	Set	d web tings ssibility

Preserve Favorites website o	data		
Keep cookies and temporary Inte websites to retain preferences ar	rnet files that en nd display faster.	able your favorite	
Temporary Internet files and	d website files		
Copies of webpages, images, and viewing.	d media that are s	aved for faster	
Cookies and website data			
Files or databases stored on your preferences or improve website p	r computer by we performance.	bsites to save	
History			
List of websites you have visited.			
Download History			
List of files you have downloaded	l.		
Form data			
Saved information that you have	typed into forms		
Passwords			
Saved passwords that are autom to a website you've previously vis	atically filled in wl sited.	nen you sign in	
Tracking Protection, ActiveX	Filtering and D	o Not Track	
A list of websites excluded from f	filtering, data use	d by Tracking ly be sharing detai	s
about your visit, and exceptions	to Do Not Track r	equests.	~
		_	
the state of the second second second	Delete	Cancel	٦

Slika 1

Slika 2

U drugom koraku potrebno je urediti postavke Adobe Reader-a.

Ponovo otvorite **Internet options** klikom na dugme **Programi**(Programs), kliknete **Podesi program** (Set programs) kao na slici ispod.

Internet Options ?							
General Sec	curity Privacy C	ontent Connections	Programs	Advanced			
Opening Int	ternet Explorer —						
	Choose how you o	oen links.					
	Let Internet Explorer decide 🗸 🗸						
[Open Internet Explorer tiles on the desktop						
Manage add	d-ons						
	Enable or disable b installed in your sys	rowser add-ons stem.	Manage a	dd-ons			
HTML editin	g						
9	Choose the program that you want Internet Explorer to use for editing HTML files.						
Η	fTML editor:	Word (desktop)		~			
Internet pro	ograms						
Choose t for other e-mail.	the programs you v r Internet services	vant to use , such as	Set prog	jrams			
File associat	tions						
Choose t Internet	the file types that Explorer to open b	you want yy default.	Set assoc	iations			
		ОК	Cancel	Apply			

Slika 3

Klikom na Set your default programs (slika 4)

Choose the programs that Windows uses by default



Slika 4

Otvoriće se prozorčić u kojem ćete moći postaviti Adobe Acrobat Reader DC kao osnovni program za otvaranje PDF dokumenata (slika 5).

Adobe Acrobe Readed DC is the trugted danded for reliably viewing, printing, signing and commenting on PDF decuments. It's the only PDF viewer that can open and interact with all types of PDF content – including forms and multimedia – and is available across leading deatap and mobile device platforms.
This program has 7 out of 8 defaults
Set this program as default Use the selected program to open all file types and protocols it can open by default.
ſh



Klikom na **Choose defaults for this program** otvoriće se prozor za izbor opcija koje treba označiti, kliknete **Select i Save** nakon izbora svih opcija.

Set associations for a p	rogram				
Select the extensions you want	this program to open by default, and then clic	k Save.			
Adobe Acrobat Reader I Adobe Systems Incorpo	DC rated				
Select All					
Name	Description	Current Default			
Extensions					
.acrobatsecuritysetting	Adobe Acrobat Security Settings Document	Adobe Acrobat Reader DC			
✓ 📆 .fdf	Adobe Acrobat Forms Document	Adobe Acrobat Reader DC			
🗹 🛐 .pdf	PDF File	Čitač			
🗹 📆 .pdfxml	Adobe Acrobat PDFXML Document	Adobe Acrobat Reader DC			
J.pdx	Acrobat Catalog Index	Adobe Acrobat Reader DC			
🖌 📷 .xdp	Adobe Acrobat XML Data Package File	Adobe Acrobat Reader DC			
🗹 📆 .xfdf	Adobe Acrobat Forms Document	Adobe Acrobat Reader DC			
Protocols					
ACROBAT	URL:Acrobat Protocol	Adobe Acrobat Reader DC			

Slika 6